

B4M35PAG - Paralelní algoritmy



<https://cw.fel.cvut.cz/wiki/courses/pag/start>

Přemysl Šůcha

email: suchap@cvut.cz

homepage: <http://people.ciirc.cvut.cz/suchap>

Organization and Contents



Organization and Contents

#	Title	Chapter
1	Introduction to Parallel Computing	Chapter 2
2	Principles of Parallel Algorithms Design	Chapter 3
3	Basic Communication Operations	Chapter 4
4	Analytical Modeling of Parallel Algorithms	Chapter 5
5	Matrix Algorithms	Chapter 8
6	Algorithms for Linear Algebra	Chapter 8
7	Sorting, Test	Chapter 9
8	Parallel Accelerators	
9	Graph Algorithms I.	Chapter 10
10	Graph Algorithms II	Chapter 10
11	Combinatorial Algorithms	Chapter 11
12	Dynamic Programming	Chapter 12
13	Fast Fourier Transform	Chapter 13

Motivation

- TOP500 (www.top500.org) - June 2019

ARM architecture
microprocessor
designed by
Fujitsu


Rank	System	Cores	Rmax (TFlop/s)	Rpeak (TFlop/s)	Power (kW)
1	Supercomputer Fugaku - Supercomputer Fugaku, A64FX 48C 2.2GHz, Tofu interconnect D, Fujitsu RIKEN Center for Computational Science Japan	7,630,848	442,010.0	537,212.0	29,899
2	Summit - IBM Power System AC922, IBM POWER9 22C 3.07GHz, NVIDIA Volta GV100, Dual-rail Mellanox EDR Infiniband, IBM DOE/SC/Oak Ridge National Laboratory United States	2,414,592	148,600.0	200,794.9	10,096
3	Sierra - IBM Power System AC922, IBM POWER9 22C 3.1GHz, NVIDIA Volta GV100, Dual-rail Mellanox EDR Infiniband, IBM / NVIDIA / Mellanox DOE/NNSA/LLNL United States	1,572,480	94,640.0	125,712.0	7,438
4	Sunway TaihuLight - Sunway MPP, Sunway SW26010 260C 1.45GHz, Sunway, NRCPC National Supercomputing Center in Wuxi China	10,649,600	93,014.6	125,435.9	15,371
5	Perlmutter - HPE Cray EX235n, AMD EPYC 7763 64C 2.45GHz, NVIDIA A100 SXM4 40 GB, Slingshot-10, HPE DOE/SC/LBNL/NERSC United States	706,304	64,590.0	89,794.5	2,528

6D mash/torus
interconnect

260-core RISC
many-core
processor designed
by the National High
Performance
Integrated Circuit
Design Center in
Shanghai

Recent Highlights in Parallel Computing

- In March 2016, **AlphaGo** beat Lee Sedol, a 9-dan professional. AlphaGo ran on 48 CPUs and 8 GPUs.
- In June 2016, Ford Using Deep Learning for Lane Detection - new sub-centimeter accurate approach to estimate a moving vehicle's position within a lane in real-time
- Tesla announces a AI neural network training supercomputer (Dojo) on August 19, 2021.



Parallel Computing Platforms

**Ananth Grama, Anshul Gupta,
George Karypis, and Vipin Kumar**

To accompany the text ``Introduction to Parallel Computing",
Addison Wesley, 2003.

Topic Overview

- Parallel Computing Platforms
- Communication Model of Parallel Platforms
- Physical Organization of Parallel Platforms
- Interconnection Networks for Parallel Computers
- Communication Costs in Parallel Machines
- Routing Mechanisms for Interconnection Networks
- Mapping Techniques

Parallel Computing Platforms

- An explicitly parallel program must **specify concurrency and interaction** between concurrent subtasks.
- The former is sometimes also referred to as the **control structure** and the latter as the **communication model**.


Control Structure of Parallel Programs

- Parallelism can be expressed at various levels of **granularity** - from instruction level to processes.
- Between these extremes exist a range of **models**, along with corresponding architectural support.

Control Structure of Parallel Programs

- Processing units in parallel computers either operate under the centralized control of a **single control** unit or **work independently**.
- If there is a single control unit that dispatches the same instruction to various processors (that work on different data), the model is referred to as single instruction stream, multiple data stream (**SIMD**).
- If each processor has its own control unit, each processor can execute different instructions on different data items. This model is called multiple instruction stream, multiple data stream (**MIMD**).

SIMD and MIMD Processors



A typical SIMD architecture (a) and a typical MIMD architecture (b).


SIMD Processors

- Variants of this concept have found use in co-processing units such as the **MMX, SSE, AVX, ... units** in Intel processors and **DSP chips** such as the Sharc.
- SIMD relies on the regular structure of computations (such as those in **image processing**).
- It is often necessary to selectively **turn off operations** on certain data items. For this reason, most SIMD programming paradigms allow for an "activity mask", which determines if a processor should participate in a computation or not.


Conditional Execution in SIMD Processors

```
if (B == 0)
    C = A;
else
    C = A/B;
```


(a)



Initial values



Step 1



Step 2

(b)

Executing a conditional statement on an SIMD computer with four processors: (a) the conditional statement; (b) the execution of the statement in two steps.

MIMD Processors

- In contrast to SIMD processors, MIMD processors can execute **different programs on different processors**.
- A variant of this, called **single program multiple data streams (SPMD)** executes the same program on different processors.
- It is easy to see that SPMD and MIMD are closely related in terms of programming flexibility and underlying architectural support.
- Single instruction, multiple thread (**SIMT**) is an execution model where SIMD is combined with multithreading.

SIMD-MIMD Comparison

- SIMD computers require less hardware than MIMD computers (**single control unit**).
- However, since **SIMD processors are specially designed**, they tend to be expensive and have long design cycles.
- Not all applications are **naturally suited to SIMD** processors.
- In contrast, platforms supporting the **SPMD paradigm can be built from inexpensive off-the-shelf components** with relatively little effort in a short amount of time.


Communication Model of Parallel Platforms

- There are **two primary forms of data exchange** between parallel tasks - accessing a shared data space and exchanging messages.
- Platforms that provide a shared data space are called **shared-address-space machines** or multiprocessors.
- Platforms that support messaging are also called **message passing platforms** or multicomputers.

Shared-Address-Space Platforms

- Part (or all) of the memory is accessible to all processors.
- Processors interact by modifying data objects stored in this shared-address-space.
- If the time taken by a processor to access any memory word in the system global or local is identical, the platform is classified as a uniform memory access (**UMA**), else, a non-uniform memory access (**NUMA**) machine.

NUMA and UMA Shared-Address-Space Platforms



Typical shared-address-space architectures: (a) Uniform-memory access shared-address-space computer; (b) Uniform-memory-access shared-address-space computer with caches and memories; (c) Non-uniform-memory-access shared-address-space computer with local memory only.

NUMA and UMA

Shared-Address-Space Platforms

- The distinction between NUMA and UMA platforms is **important from the point of view of algorithm design**. NUMA machines require locality from underlying algorithms for performance.
- Programming these platforms is easier since reads and writes are implicitly visible to other processors.
- However, **read-write data to shared data must be coordinated** (this will be discussed in greater detail when we talk about threads programming).
- Caches in such machines require coordinated access to multiple copies. This leads to the **cache coherence** problem.

Message-Passing Platforms

- These platforms comprise of a set of processors and their **own (exclusive) memory**.
- Instances of such a view come naturally from **clustered workstations** and non-shared-address-space multicomputers.
- These platforms are programmed using (variants of) **send and receive primitives**.
- Libraries such as **MPI** and PVM provide such primitives.

Message Passing

vs.

Shared Address Space Platforms

- Message passing requires **little hardware support**, other than a network.
- **Shared address space platforms can easily emulate message passing.** The reverse is more difficult to do (in an efficient manner).

Physical Organization of Parallel Platforms

We begin this discussion with an ideal parallel machine called **Parallel Random Access Machine**, or **PRAM**.

Architecture of an Ideal Parallel Computer

- A natural **extension** of the Random Access Machine (RAM) serial architecture is the Parallel Random Access Machine, or PRAM.
- PRAMs consist of **p processors** and a **global memory of unbounded size** that is **uniformly accessible** to all processors.
- Processors share a **common clock** but may execute **different instructions** in each cycle.

Architecture of an Ideal Parallel Computer

- Depending on how simultaneous memory accesses are handled, PRAMs can be divided into four subclasses.
 - Exclusive-read, exclusive-write (EREW) PRAM.
 - Concurrent-read, exclusive-write (CREW) PRAM.
 - Exclusive-read, concurrent-write (ERCW) PRAM.
 - Concurrent-read, concurrent-write (CRCW) PRAM.

Architecture of an Ideal Parallel Computer


- What does concurrent write mean, anyway?
 - Common: write only if all values are identical.
 - Arbitrary: write the data from a randomly selected processor.
 - Priority: follow a predetermined priority order.
 - Sum: Write the sum of all data items.

Interconnection Networks for Parallel Computers


- Interconnection networks carry **data between processors** and to memory.
- Interconnects are made of **switches** and **links** (wires, fiber).
- Interconnects are classified as static or dynamic.
- **Static networks** consist of point-to-point communication links among processing nodes and are also referred to as *direct* networks.
- **Dynamic networks** are built using switches and communication links. Dynamic networks are also referred to as *indirect* networks.

Network Topologies: Completely Connected Network

- Each processor is connected to every other processor.
- The **number of links** in the network scales as $O(p^2)$.
- While the **performance scales very well**, the hardware complexity is **not realizable** for large values of p .
- These networks are **static counterparts of crossbars**.




static network




Network Topologies: Star Connected Network

- Every node is connected only to a common node at the center.
- **Distance** between any pair of nodes is $O(1)$. However, the central node becomes a bottleneck.
- In this sense, **star connected networks are static counterparts of buses.**



static network




dynamic network


Network Topologies: Linear Arrays, Meshes, and k - d Meshes

- In a **linear array**, each node has two neighbors, one to its left and one to its right. If the nodes at either end are connected, we refer to it as a **1-D torus** or a ring.
- A **generalization to 2 dimensions** has nodes with 4 neighbors, to the north, south, east, and west.
- A further generalization to d dimensions has nodes with $2d$ neighbors.
- A special case of a d -dimensional mesh is a **hypercube**. Here, $d = \log p$, where p is the total number of nodes.

Network Topologies: Linear Arrays




(a)




(b)

Linear arrays: (a) with no wraparound links; (b) with wraparound link.


Network Topologies: Two- and Three Dimensional Meshes



(a)




(b)



(c)

Two and three dimensional meshes: (a) 2-D mesh with no wraparound; (b) 2-D mesh with wraparound link (2-D torus); and (c) a 3-D mesh with no wraparound.

Network Topologies: Hypercubes and their Construction



Construction of hypercubes from hypercubes of lower dimension.

Network Topologies: Properties of Hypercubes

- The **distance** between any two nodes is at most $\log p$.
- Each node has $\log p$ **neighbors**.
- The distance between two nodes is given by the number of bit positions at which the two nodes differ.

Evaluating Static Interconnection Networks

- **Diameter:** The distance between the farthest two nodes in the network. The diameter of a linear array is $p - 1$, that of a mesh is $2(\sqrt{p} - 1)$, that of a tree and hypercube is $\log p$, and that of a completely connected network is $O(1)$.
- **Bisection Width:** The minimum number of wires you must cut to divide the network into two equal parts. The bisection width of a linear array and tree is 1 , that of a mesh is \sqrt{p} , that of a hypercube is $p/2$ and that of a completely connected network is $p^2/4$.
- **Cost:** The number of links or switches (whichever is asymptotically higher) is a meaningful measure of the cost.
- **Arc Connectivity:** is the minimum number of arcs that must be removed from the network to break it into two disconnected networks

Evaluating Static Interconnection Networks

Network	Diameter	Bisection Width	Arc Connectivity	Cost (No. of links)
Completely-connected	1	$p^2/4$	$p - 1$	$p(p - 1)/2$
Star	2	1	1	$p - 1$
Complete binary tree	$2 \log((p + 1)/2)$	1	1	$p - 1$
Linear array	$p - 1$	1	1	$p - 1$
2-D mesh, no wraparound	$2(\sqrt{p} - 1)$	\sqrt{p}	2	$2(p - \sqrt{p})$
2-D wraparound mesh	$2\lfloor\sqrt{p}/2\rfloor$	$2\sqrt{p}$	4	$2p$
Hypercube	$\log p$	$p/2$	$\log p$	$(p \log p)/2$
Wraparound k -ary d -cube	$d\lfloor k/2\rfloor$	$2k^{d-1}$	$2d$	dp

Communication Costs in Parallel Machines

- Along with idling and contention, **communication is a major overhead** in parallel programs.
- The **cost of communication** is dependent on a variety of features including the **programming model** semantics, the **network topology**, **data handling and routing**, and associated **software protocols**.

Message Passing Costs in Parallel Computers

- The **total time to transfer a message** over a network comprises of the following:
 - *Startup time* (t_s): Time spent at sending and receiving nodes (executing the routing algorithm, programming routers, etc.).
 - *Per-hop time* (t_h): This time is a function of number of hops and includes factors such as **switch latencies**, network delays, etc.
 - *Per-word transfer time* (t_w): This time includes all **overheads that are determined by the length of the message**. This **includes bandwidth** of links, error checking and correction, etc.

Store-and-Forward Routing


- A **message traversing multiple hops is completely received** at an intermediate hop before being forwarded to the next hop.
- The total communication cost for a message of **size m** words to traverse **l communication links** is

$$t_{comm} = t_s + (mt_w + t_h)l.$$

- In most platforms, t_h is small and the above expression can be approximated by

$$t_{comm} = t_s + mlt_w.$$

Routing Techniques



Passing a message from node P_0 to P_3 (a) through a store-and-forward communication network; (b) and (c) extending the concept to cut-through routing. The shaded regions represent the time that the message is in transit. The startup time associated with this message transfer is assumed to be zero.

Cut-Through Routing

- Takes the concept of packet routing to an extreme by further dividing messages into basic units called **flits**.
- Since flits are typically **small**, the header information must be minimized.
- This is done by forcing all flits to take **the same path**, in sequence.
- A tracer message first programs all intermediate routers. All flits then take the same route.
- Error **checks are performed on the entire message**, as opposed to flits.
- No **sequence numbers are needed**.

Simplified Cost Model for Communicating Messages

- The cost of communicating a message between two nodes l hops away using cut-through routing is given by

$$t_{comm} = t_s + lt_h + t_w m.$$

- In this expression, **t_h is typically smaller than t_s and t_w** . For this reason, the second term in the RHS does not show, particularly, **when m is large**.
- Furthermore, it is **often not possible to control routing and placement of tasks**.
- For these reasons, we can approximate the cost of message transfer by

$$t_{comm} = t_s + t_w m.$$


Simplified Cost Model for Communicating Messages

- It is important to note that the original expression for communication time is valid for only **uncongested networks**.
- If a link takes multiple messages, the corresponding t_w term **must be scaled up by the number of messages**.
- **Different communication patterns congest different networks to varying extents.**
- It is important to understand and account for this in the communication time accordingly.

Routing Mechanisms for Interconnection Networks

- How does one compute the route that a message takes from source to destination?
 - **Routing must prevent deadlocks** - for this reason, we use dimension-ordered or **e-cube routing**.
 - **Routing must avoid hot-spots** - for this reason, two-step routing is often used. In this case, a message from source s to destination d is first sent to a randomly chosen intermediate processor i and then forwarded to destination d .

Routing Mechanisms for Interconnection Networks



Routing a message from node P_s (010) to node P_d (111) in a three-dimensional hypercube using E-cube routing.

Mapping Techniques for Graphs

- Often, we need to **embed a known communication pattern into a given interconnection topology.**
- We may have an **algorithm designed for one network,** which we are porting to another topology.

For these reasons, it is useful to understand **mapping between graphs.**

Mapping Techniques for Graphs: Metrics

- When mapping a graph $G(V,E)$ into $G'(V',E')$, the following metrics are important:
- The maximum number of edges mapped onto any edge in E' is called the **congestion** of the mapping.
- The maximum number of links in E' that any edge in E is mapped onto is called the **dilation** of the mapping.
- The ratio of the number of nodes in the set V' to that in set V is called the **expansion** of the mapping.

Embedding a Linear Array into a Hypercube

- A linear array (or a ring) composed of 2^d nodes (labeled 0 through $2^d - 1$) can be embedded into a d -dimensional hypercube by mapping node i of the linear array onto node
- **$G(i, d)$ of the hypercube.** The function $G(i, x)$ is defined as follows:

$$G(0, 1) = 0$$

$$G(1, 1) = 1$$



$$G(i, x + 1) = \begin{cases} G(i, x), & i < 2^x \\ 2^x + G(2^{x+1} - 1 - i, x), & i \geq 2^x \end{cases}$$

Embedding a Linear Array into a Hypercube

The function G is called the *binary reflected Gray code* (RGC).

Since adjoining entries ($G(i, d)$ and $G(i + 1, d)$) differ from each other at only one bit position, corresponding processors are mapped to neighbors in a hypercube. Therefore, the **congestion, dilation, and expansion of the mapping are all 1.**

Embedding a Linear Array into a Hypercube: Example




(a) A three-bit reflected Gray code ring; and (b) its embedding into a three-dimensional hypercube.

Embedding a Mesh into a Hypercube

- A $2^r \times 2^s$ wraparound mesh can be mapped to a 2^{r+s} node hypercube by mapping node (i, j) of the mesh onto node $G(i, r-1) \parallel G(j, s-1)$ of the hypercube (where \parallel denotes **concatenation of the two Gray codes**).

Embedding a Mesh into a Hypercube




(a) A 4×4 mesh illustrating the mapping of mesh nodes to the nodes in a four-dimensional hypercube; and (b) a 2×4 mesh embedded into a three-dimensional hypercube.

Once again, the congestion, dilation, and expansion of the mapping is 1.


Embedding a Mesh into a Linear Array

- Since a **mesh has more edges than a linear array**, we will not have an optimal congestion/dilation mapping.
- We first examine the mapping of a linear array into a mesh and then invert this mapping.
- This gives us an optimal mapping (in terms of congestion).

Embedding a Mesh into a Linear Array: Example



(a) Mapping a linear array into a 2D mesh (congestion 1).



(b) Inverting the mapping - mapping a 2D mesh into a linear array (congestion 5)

(a) Embedding a 16 node linear array into a 2-D mesh; and (b) the inverse of the mapping. Solid lines correspond to links in the linear array and normal lines to links in the mesh.