

B4M36ESW: Efficient software

Lecture 5: Scalable synchronization

Michal Sojka

`michal.sojka@cvut.cz`



June 17, 2019

Synchronization

- **Multi-core** CPUs are today's norm, many-core CPUs will come tomorrow
- To take advantage of such a hardware, **parallel (multi-threaded) programs** must be run on them
- It is not useful when the threads are completely independent, i.e. threads have to **communicate (synchronize)**
- Basic forms of synchronization:
 - Mutual exclusion (e.g. access to shared data)
 - Producer-consumer (e.g. database waits for requests)
 - ...

Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations

Naive synchronization

Mutual exclusion

Data should be modified at most by one thread at a time:

```
bool locked;
```

```
void func() {  
    while (locked == true)  
        /* busy wait */;  
    locked = true;  
    data++;  
    locked = false;  
}
```

Terminology: code in the “locked” region is called *critical section*

Problems:

- 1 Checking and setting the lock is not atomic
- 2 Compiler can optimize out all accesses to *locked*
- 3 Compiler can move access to data out of critical section
- 4 Hardware can reorder memory accesses even if compiler does not
- 5 Can easily deadlock
- 6 Busy waiting wastes energy

Quote

Implementing a correct synchronization primitive is like committing the perfect crime. There are at least 50 things that can go wrong, and if you are a highly experienced genius, you -might- be able to anticipate and handle 25 of them.

— Paul McKenney

<https://lwn.net/ml/linux-kernel/20190608160620.GH28207@linux.ibm.com/>

Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations

Atomic operations

■ Example of non-atomic increment:

- C expression: `data++`;
- Assembler (x86): `inc ($data)` – atomic (uninterruptible) on a single CPU
- Hardware (as seen from other CPUs): memory bus read, ALU, memory bus write

CPU0	CPU1	data
bus read		0
ALU	bus read	0
bus write	ALU	1
	bus write	1

■ Atomic operations ensure that the operation (typically read-modify-write) is atomic (uninterruptible) even at the hardware (bus) level.

- compare-and-swap/CAS instruction (x86: `cmpxchg`)
- In C: `TYPE __atomic_exchange_n(TYPE *ptr, TYPE val, int memorder)`
Atomically set `*ptr` to `val` and return old value of `*ptr`.

```

void lock() {
    while (locked == true)
        /* busy wait */;
    locked = true;
}

void lock() {
    while (__atomic_exchange_n(&locked, true,
                               ...) == true)
        /* busy wait */;
}

```

Atomic operations in C and C++

- For long time, atomic operations were not standardized in C/C++
 - Solution: Incompatible compiler extensions, inline assembler
- C11, C++11 introduced thread-aware memory model and defined platform independent atomic operations
- C11: `stdatomic.h`, `atomic_*` functions
- C++11
 - `std::atomic` template
 - `std::atomic<int> x;`
`x++;` *// atomic increment*

Compiler optimizations

```
bool locked;
```

```
while (locked)
```

```
{}
```

```
locked = true;
```

```
data++;
```

```
locked = false;
```

⇒

```
#define barrier() \
```

```
asm volatile("" : : : "memory"
```

```
volatile bool locked;
```

```
while (locked)
```

```
{}
```

```
locked = true;
```

```
barrier();
```

```
data++;
```

```
barrier();
```

```
locked = false;
```

- Compiler expects the memory is only modified by the program being compiled
- Locked seems to be useless ⇒ optimize out
- Compiler is free to reorder operations as long as the result of the computation is the same

Compiler optimizations cont.

- Defining the variable volatile makes all accesses “volatile” i.e. slow.
- Sometimes, we need only certain accesses to have volatile semantics and the rest can be optimized:

```
#define ACCESS_ONCE(x) (*(volatile typeof(x) *)&(x))
#define LOAD_SHARED(p) ACCESS_ONCE(p)
#define STORE_SHARED(x, v) ({ ACCESS_ONCE(x) = (v); })
```

```
#define barrier() asm volatile("" : : : "memory")
```

- The macro barrier is only a **compiler barrier**, not hardware barrier, i.e., the compiler will not reorder generated instructions.

Hardware reordering

- Different CPU architectures implement different memory consistency models
- Some operations can be reordered with respect to other operations

Type	Alpha	ARMv7	PA-RISC	POWER	SPARC RMO	SPARC PSO	SPARC TSO	x86	x86 oostore	AMD64	IA-64	z/Architecture
Loads → loads	Y	Y	Y	Y	Y	N	N	N	Y	N	Y	N
Loads → stores	Y	Y	Y	Y	Y	N	N	N	Y	N	Y	N
Stores → stores	Y	Y	Y	Y	Y	Y	N	N	Y	N	Y	N
Stores → loads	Y	Y	Y	Y	Y	Y	Y	Y	Y	Y	Y	Y
Atomic → loads	Y	Y	N	Y	Y	N	N	N	N	N	Y	N
Atomic → stores	Y	Y	N	Y	Y	Y	N	N	N	N	Y	N
Dependent loads	Y	N	N	N	N	N	N	N	N	N	N	N
Incoherent inst. cache pipeline	Y	Y	N	Y	Y	Y	Y	Y	Y	N	Y	

Source: Wikipedia

- x86 can reorder stores after loads, i.e. data can be read before other CPUs see `locked` set to true!
- Why? Stores may have to wait for cache-line ownership. Not waiting with subsequent reads improves **performance**.
- **Solution:** Insert memory barrier instructions.
 - e.g. `mfence`, `lfence` instructions (on x86), `dmb` (on ARM).
 - RCU implementations at the end of this lecture use `smb_mb()` function, which is a platform independent wrapper of these instructions.

Specifying memory ordering requirements in C/C++

```
std::atomic<int> x;  
x.load(order);  
w.store(0, order);
```

- `order` specifies how regular, non-atomic memory accesses are to be ordered around an atomic operation
 - relaxed: no overhead, no order guarantee
 - consume
 - acquire
 - release
 - `acq_rel`,
 - `seq_cst`: high overhead, sequential consistency
- Depending on the CPU architecture, different `orders` cause the compiler to generate barrier instructions (e.g., `lfence` on x86)

Deadlock

- Example:
 - Single-core system
 - Spinning lock
 - Two threads low- and high-priority

```

LP_thread      HP_thread
-----      -----
lock();
data++;
      →      ←      →
                lock(); // deadlock

```

- **Solution:** When the lock is not available, ask the OS scheduler to put your thread to sleep and wake you up after the lock is available
 - Problem: atomicity of checking the lock and going to sleep
 - Requires implementation in the OS kernel

Spinlocks

- The lock (from our initial example) that does not involve OS scheduler and waits by spinning (looping, busy waiting) is called a **spin lock**.
- Applications almost never need to use spin locks.
 - It wastes energy, CPU time and can lead to deadlocks (see above).
- Spin locks are, however, used in operating system kernels in contexts, where it is not possible to sleep.
 - Only threads (tasks, processes) can sleep.
 - Interrupt handlers cannot sleep.
 - Hence **device drivers** often use spin locks.
 - OS scheduler must also use spin locks, because it cannot put itself to sleep.

Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations

Cost of atomic operations & barriers


16-CPU 2.8GHz Intel X5550 (Nehalem) System

Operation	Cost (ns)	Ratio
Clock period	0.4	1.0
“Best-case” CAS	12.2	33.8
Best-case lock	25.6	71.2
Single cache miss	12.9	35.8
CAS cache miss	7.0	19.4
Single cache miss (off-core)	31.2	86.6
CAS cache miss (off-core)	31.2	86.5
Single cache miss (off-socket)	92.4	256.7
CAS cache miss (off-socket)	95.9	266.4

Source: Paul E. McKenney, IBM

- Atomic operations are costly (here 19–266 times slower than non-atomic operations)
- Barriers are typically cheaper (weak barriers more that full barriers)

Cost of atomic operations & laws of physics



Every CPU experiences a cache miss, because other CPUs access the variable as well
 No cache miss ⇒ much faster


Locking overhead

- Classical locks are typically implemented with atomic instructions and ensure that lock manipulation is not reordered with critical section content.

```
pthread_mutex_lock(mutex);
x++;
pthread_mutex_unlock(mutex);
```

- Uncontended case: during lock(), mutex is not in the cache, during unlock() it is
- Contended case: mutex is not in the cache even during unlock, because there is (probably) another CPU trying to lock the mutex and thus “stealing” the lock from mutex-owner’s cache

Single-instruction critical sections protected by a lock



Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations

Kernel semaphores

- Each system call adds overhead (≈ 100 cycles on modern HW)
- It is preferable to use “fine-grain” locking, i.e. locks protect as little data as possible to prevent lock contention.
- If fine-grain locking is effective the lock is not contended and threads rarely have to sleep, but always pay the syscall overhead!
- That's not efficient – the solution in Linux is called **futex**.

Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations

Futex

Fast Userspace Mutex

- Uncontended mutex never goes to kernel
- It uses atomic instruction
`cmpxchg(val, expct, new) → prev`
- `futex_wait()` and `futex_wake()` are system calls that are called only in case of contention

```
class mutex {
public:
    mutex() : val (0) { }

    void lock() {
        int c;
        if ((c = cmpxchg (val, 0, 1)) != 0) {
            if (c != 2)
                c = xchg (val, 2);
            while (c != 0) {
                futex_wait (&val, 2);
                c = xchg (val, 2);
            }
        }
    }

    void unlock() {
        if (atomic_dec (val) != 1) {
            val = 0;
            futex_wake (&val, 1);
        }
    }

private:
    int val;
};
```

U. Drepper, *Futexes Are Tricky*, 2011,
 Online: <https://www.akkadia.org/drepper/futex.pdf>

Futex uses

- Futex primitive can be used to implement the following higher-level synchronization mechanisms:
 - Mutexes
 - Semaphores
 - Conditional variables
 - Thread barriers
 - Read-write locks
- Today, `pthread_mutex_t` in Linux is implemented via futex.
- JVM's synchronization via Mark word and thin/fat locking is conceptually the same as futex (see next lecture)


Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations

The problem of mutex

Mutual exclusion in massively parallel **read-mostly workload**

- 1 Lock/unlock overhead
- 2 Dead time during updates




Read-mostly workload

- Many real-world workloads are “read-mostly”
- Caching – Most users only read the data. The cache is updated only from time to time (new article is published, etc.)
 - Web site cache (template rendering)
 - Content delivery network (CDN)
 - File system access
 - Domain Name System (DNS)
 - ...
- Maintaining consistency while updating – synchronization between readers and updaters (writers)


Read-Write lock

- Classical solution – read-write lock
- Multiple readers can read simultaneously
- Update blocks all readers



- Can be implemented on top of mutex(es)
- Scales badly

We want this




- Updater does not block readers
- Is that possible? **Yes**
- For what cost? **See next slides**

Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations


Read-side scalability of synchronization primitives




- RCU is **scalable** – typically it scales almost linearly up to hundreds or thousands of CPUs
- Locking does **not scale** (see next slide)

Locking scalability

- Zoomed in version of the previous graph




Updating an RCU-protected list



- 1 Original list
- 2 Copy B
- 3 Update B to D
- 4 Make the updated element visible to readers
- 5 Wait after all readers stop accessing B and free it

Steps 1–4 are trivial, making step 5 efficient is why RCU is needed!

How does RCU know when no reader access old data?



- **No explicit (and expensive) tracking** of each reader (e.g. no reference counting, no locking in readers)
- RCU uses **indirect** way of determining the end of all read-side sections
- In certain implementations (QSBR) read-side has **zero overhead**


Main mechanisms of RCU

- 1 Publishing of updates (3→4)
 - Ensure that updated data reach memory before the updated pointer
 - Compiler and memory barrier \Rightarrow `rcu_assign_pointer()`
- 2 Accessing new versions of data (how readers traverse the list)
 - Ensure that we see all the updates made before publishing
 - Compiler and memory barrier \Rightarrow `rcu_dereference()`
- 3 Waiting for all readers to finish
 - **The tricky part!** \Rightarrow `synchronize_rcu()`

Note: RCU and Java

- Does it makes sense to use RCU in Java?
- No, because JVM decides when to free objects by using a tracing garbage collector. Garbage collectors have much higher overhead than RCU (stop-the-world, marking overhead, ...).

RCU concepts and API



RCU read-side critical section

```
rcu_read_lock(); /* Start critical section. */  
p = rcu_dereference(cptr);  
/* *p guaranteed to exist. */  
do_something_with(p);  
rcu_read_unlock(); /* End critical section. */  
/* *p might be freed!!! */
```

- `rcu_read_lock()/unlock()` and `rcu_dereference()` are cheap, sometimes *nop*.
- Updaters are more heavy-weight.

Pitfalls in read-side access (without RCU)

See [PerfBook, 15.3.2]

Instead of:

```
p = rcu_dereference(cptr);
```

Example

```
1 data_t *p = cptr;
2 use(p->field1);
3 use(p->field2);
4 ...
5 data_t *p = cptr;
6 use(p->field1);
7 use(p->field2);
```

- 1 On DEC Alpha, line 1 can be executed after line 2.
- 2 Compiler can omit the load at line 5 and use the value from line 1.
- 3 Compiler can load `cptr` multiple times – e.g. `cptr` can be reloaded between lines 2 and 3. If `*cptr` changes its value, lines 2 and 3 will use different value of `p`.

RCU updater

```
pthread_mutex_lock(&updater_lock);  
old_p = cptr;  
*new_p = *old_p;           // copy if needed  
new_p->... = ...;  
rcu_assign_pointer(cptr, new_p); // update  
pthread_mutex_unlock(&updater_lock);  
synchronize_rcu();         // wait for grace period end  
free(old_p);
```

- Updater can use locks, because we deal with read-mostly workload, where updates are infrequent.
- Locks are not needed if there is just one updater

Outline

- 1 Naive synchronization
 - Problems
 - Non-atomic data manipulation
 - Unwanted compiler optimizations
 - Reordering at hardware level
 - Deadlock
 - Busy waiting (spinning)
- 2 Cost of atomic operations and barriers
- 3 Kernel semaphores
- 4 Futex
- 5 Read-mostly workload
- 6 Read-Copy-Update (RCU)
 - RCU implementations

How does it work?

- Many implementations possible
- Trade-off between read-side overhead and constraints of application structure
- We will look at the following implementations:
 - Quiescent-state based reclamation (QSBR)
 - General-purpose
- See <https://www.efficios.com/pub/rcu/urcu-suppl.pdf>, Appendix D for more implementations and details.

Quiescent-state based reclamation (QSBR)

```

// Protects registry from concurrent accesses
pthread_mutex_t rcu_gp_lock =
    PTHREAD_MUTEX_INITIALIZER;

LIST_HEAD(registry);

struct rcu_reader {
    // bit 0 = online, bits 1-63 = counter
    unsigned long ctr;
    struct list_head node;
    pthread_t tid;
};

// per-thread variable
struct rcu_reader __thread rcu_reader;

void rcu_register_thread(void) {
    rcu_reader.tid = pthread_self();
    mutex_lock(&rcu_gp_lock);
    list_add(&rcu_reader.node, &registry);
    mutex_unlock(&rcu_gp_lock);
    rcu_thread_online();
}

void rcu_unregister_thread(void) {
    rcu_thread_offline();
    mutex_lock(&rcu_gp_lock);
    list_del(&rcu_reader.node);
    mutex_unlock(&rcu_gp_lock);
}

#define RCU_GP_ONLINE 0x1
#define RCU_GP_CTR 0x2

// global counter - note: not accessed with atomic instr.
unsigned long rcu_gp_ctr = RCU_GP_ONLINE;

static inline void rcu_read_lock(void) {}
static inline void rcu_read_unlock(void) {}

// Every thread must call this function periodically
// outside of read-side critical section.
// Note 1: There is no atomic instruction and barriers are
// cheaper than atomic instructions.
// Note 2: This is not called per read-side critical section
// only "from time to time" e.g. in the main program
// loop.
static inline void rcu_quiescent_state(void) {
    smp_mb();
    STORE_SHARED(rcu_reader.ctr, LOAD_SHARED(rcu_gp_ctr));
    smp_mb();
}

// call before a blocking system call
static inline void rcu_thread_offline(void) {
    smp_mb();
    STORE_SHARED(rcu_reader.ctr, 0);
}

// call after return from a blocking system call
static inline void rcu_thread_online(void) {
    STORE_SHARED(rcu_reader.ctr, LOAD_SHARED(rcu_gp_ctr));
    smp_mb();
}

```

Quiescent-state based reclamation (QSBR), cont.

```

// Updater will call these
void synchronize_rcu(void) {
    unsigned long was_online;
    was_online = rcu_reader.ctr;
    smp_mb();
    if (was_online)
        STORE_SHARED(rcu_reader.ctr, 0);
    mutex_lock(&rcu_gp_lock);
    update_counter_and_wait();
    mutex_unlock(&rcu_gp_lock);
    if (was_online)
        STORE_SHARED(rcu_reader.ctr, LOAD_SHARED(rcu_gp_ctr));
    smp_mb();
}

static void update_counter_and_wait(void) {
    struct rcu_reader *index;
    STORE_SHARED(rcu_gp_ctr, rcu_gp_ctr + RCU_GP_CTR);
    barrier();
    list_for_each_entry(index, &registry, node) {
        while (rcu_gp_ongoing(&index->ctr))
            msleep(10);
    }
}

static inline int rcu_gp_ongoing(unsigned long *ctr)
{
    unsigned long v;
    v = LOAD_SHARED(*ctr);
    return v && (v != rcu_gp_ctr);
}

```

Properties:

- Threads must call `rcu_quiescent_state()` from time to time (e.g. in the main event loop).
- Threads must call `rcu_threads_off/online` around blocking calls (e.g. `epoll_wait()`).
 - Otherwise, grace period can never end.
- Grace periods are not shared
- Long waiting \Rightarrow higher memory consumption
- Works only on 64-bit architectures – the counter must not overflow

QSBR example

Time →

	Startup	rcu_register_thread	rcu_quiescent_state @CPU0	rcu_quiescent_state @CPU1	synchronize_rcu start @CPU3	rcu_quiescent_state @CPU0	rcu_quiescent_state @CPU2	rcu_quiescent_state @CPU1	synchronize_rcu end @CPU3		synchronize_rcu start @CPU1	rcu_quiescent_state @CPU3	rcu_quiescent_state @CPU0	rcu_quiescent_state @CPU2	synchronize_rcu end @CPU1
rcl_gp_ctr	1				3						5				
CPU0 rcu_reader.ctr	1					3							5		
CPU1 rcu_reader.ctr	1							3			0				5
CPU2 rcu_reader.ctr	1						3							5	
CPU3 rcu_reader.ctr	1				0				3			5			

General-purpose RCU

```

// bit 16 = 1-bit counter (parity)
#define RCU_GP_CTR_PHASE 0x10000
// bits 0-15 = 16-bit nesting counter
#define RCU_NEST_MASK 0x0ffff
#define RCU_NEST_COUNT 0x1

unsigned long rcu_gp_ctr = RCU_NEST_COUNT;

static inline void rcu_read_lock(void)
{
    unsigned long tmp;
    tmp = rcu_reader.ctr;
    if (!(tmp & RCU_NEST_MASK)) {
        STORE_SHARED(rcu_reader.ctr, LOAD_SHARED(rcu_gp_ctr));
        smp_mb();
    } else {
        // Nested critical section does not need a barrier
        STORE_SHARED(rcu_reader.ctr, tmp + RCU_NEST_COUNT);
    }
}

static inline void rcu_read_unlock(void)
{
    smp_mb();
    STORE_SHARED(rcu_reader.ctr, rcu_reader.ctr - RCU_NEST_COUNT);
}

```

Properties:

- Does not restrict application structure
 - No need to call `rcu_quiescent_state`
 - No need to call `rcu_thread_(on|off)line` around blocking syscalls
- No counter-overflow problem (different mechanism with only 1-bit counters)
- Higher read-side overhead: memory barrier (still less than typical locks).
- Supports nesting of read-side critical sections

General-purpose RCU, cont.

```

void synchronize_rcu(void)
{
    smp_mb();
    mutex_lock(&rcu_gp_lock);
    update_counter_and_wait();
    barrier();
    update_counter_and_wait();
    mutex_unlock(&rcu_gp_lock);
    smp_mb();
}

static void update_counter_and_wait(void)
{
    struct rcu_reader *index;
    STORE_SHARED(rcu_gp_ctr, rcu_gp_ctr | RCU_GP_CTR_PHASE);
    barrier();
    list_for_each_entry(index, &registry, node) {
        while (rcu_gp_ongoing(&index->ctr))
            msleep(10);
    }
}

static inline int rcu_gp_ongoing(unsigned long *ctr)
{
    unsigned long v;
    v = LOAD_SHARED(*ctr);
    // ongoing = nesting counter > 0 and global (1-bit) counter != local counter
    return (v & RCU_NEST_MASK) && ((v | rcu_gp_ctr) & RCU_GP_CTR_PHASE);
}

```

Update benchmarks




Fig. 9. Update Overhead, 8-core Intel Xeon, Logarithmic Scale




Fig. 10. Update Overhead, 64-core POWER5+, Logarithmic Scale




Fig. 11. Impact of Update-Side Critical Section Length on Read-Side, 8-core Intel Xeon, Logarithmic Scale




Fig. 12. Impact of Update-Side Critical Section Length on Read-Side, 64-core POWER5+, Logarithmic Scale

Conclusion

- RCU is a scalable synchronization mechanism for hundreds/thousands of CPUs and read-mostly workload
- We have seen an RCU-based implementation of single-linked list, but many other common data structures can be implemented in an RCU-compatible way

References

- [PerfBook] Paul E. McKenney et al.: Is Parallel Programming Hard, And, If So, What Can You Do About It
<https://mirrors.edge.kernel.org/pub/linux/kernel/people/paulmck/perfbook/perfbook.html>
- Desnoyers, Mathieu, McKenney, Paul. E., Stern, Alan S., Dagenais, Michel R. and Walpole, Jonathan, User-Level Implementations of Read-Copy Update. IEEE Transaction on Parallel and Distributed Systems, 23 (2): 375-382 (2012).
<https://www.efficios.com/publications>
- Paul E. McKenney, What Is RCU? Guest Lecture for Technische Universität Dresden
<http://www2.rdrop.com/users/paulmck/RCU/RCU.2014.05.18a.TU-Dresden.pdf>

Appendix

- RCU is being proposed for inclusion into C++ standard:

<http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2018/p1122r2.pdf>

- RCU is patented by IBM, which freely licenses the patent to copy-left software. Userspace RCU library (copyleft – LGPL) can be used in proprietary code. The patents should expire soon.

<https://lwn.net/Articles/777519/>