# **Electromagnetic Field Theory 2**(fundamental relations and definitions)


#### Lukas Jelinek

lukas.jelinek@fel.cvut.cz Department of Electromagnetic Field Czech Technical University in Prague Czech Republic

Ver. 2017/04/03



## Maxwell('s)-Lorentz('s) Equations



Interaction with materials

$$egin{aligned} oldsymbol{D}ig(oldsymbol{r},tig) &= arepsilon_0 oldsymbol{E}ig(oldsymbol{r},tig) + oldsymbol{P}ig(oldsymbol{r},tig) \ oldsymbol{B}ig(oldsymbol{r},tig) &= \mu_0 ig(oldsymbol{H}ig(oldsymbol{r},tig) + oldsymbol{M}ig(oldsymbol{r},tig) \end{aligned}$$

Absolute majority of things happening around us is described by these equations





### **Boundary Conditions**

$$\boldsymbol{n}\left(\boldsymbol{r}\right)\times\left[\boldsymbol{E}_{1}\left(\boldsymbol{r},t\right)-\boldsymbol{E}_{2}\left(\boldsymbol{r},t\right)\right]=0$$

$$\boldsymbol{n}\left(\boldsymbol{r}\right)\times\left[\boldsymbol{H}_{1}\left(\boldsymbol{r},t\right)-\boldsymbol{H}_{2}\left(\boldsymbol{r},t\right)\right]=\boldsymbol{K}\left(\boldsymbol{r},t\right)$$

$$\boldsymbol{n}\left(\boldsymbol{r}\right)\cdot\left[\boldsymbol{B}_{1}\left(\boldsymbol{r},t\right)-\boldsymbol{B}_{2}\left(\boldsymbol{r},t\right)\right]=0$$
Normal pointing to region (1) 
$$\boldsymbol{n}\left(\boldsymbol{r}\right)\cdot\left[\boldsymbol{D}_{1}\left(\boldsymbol{r},t\right)-\boldsymbol{D}_{2}\left(\boldsymbol{r},t\right)\right]=\sigma\left(\boldsymbol{r},t\right)$$





### **Electromagnetic Potentials**

#### Lorentz('s) calibration

$$\nabla \cdot \boldsymbol{A} \Big( \boldsymbol{r}, t \Big) = -\sigma \mu \varphi \Big( \boldsymbol{r}, t \Big) - \varepsilon \mu \frac{\partial \varphi \Big( \boldsymbol{r}, t \Big)}{\partial t}$$

$$m{B}ig(m{r},tig) = 
abla imes m{A}ig(m{r},tig)$$

$$oldsymbol{B}ig(oldsymbol{r},tig) = 
abla imes oldsymbol{A}ig(oldsymbol{r},tig) = -
abla arphiig(oldsymbol{r},tig) - rac{\partial oldsymbol{A}ig(oldsymbol{r},tig)}{\partial t}$$




### **Wave Equation**

$$\Delta \mathbf{A}(\mathbf{r},t) - \sigma \mu \frac{\partial \mathbf{A}(\mathbf{r},t)}{\partial t} - \varepsilon \mu \frac{\partial^2 \mathbf{A}(\mathbf{r},t)}{\partial t^2} = -\mu \mathbf{J}_{\text{source}}(\mathbf{r},t)$$

Material parameters are assumed independent of coordinates



### Poynting('s)-Umov('s) Theorem




Energy balance in an electromagnetic system



### **Frequency Domain**

$$oldsymbol{F}ig(oldsymbol{r},tig)\in\mathbb{R}$$
  $\hat{oldsymbol{F}}ig(oldsymbol{r},\omegaig)\in\mathbb{C}$   $oldsymbol{F}ig(oldsymbol{r},tig)=rac{1}{2\pi}\int\limits_{-\infty}^{\infty}\hat{oldsymbol{F}}ig(oldsymbol{r},\omegaig)\mathrm{e}^{\mathrm{j}\omega t}d\omega$   $oldsymbol{\hat{F}}ig(oldsymbol{r},\omegaig)=\int\limits_{-\infty}^{\infty}oldsymbol{F}ig(oldsymbol{r},tig)\mathrm{e}^{-\mathrm{j}\omega t}dt$ 



Frequency domain helps us to remove explicit time derivatives





### **Phasors**

$$\hat{\boldsymbol{F}}(\boldsymbol{r}, -\omega) = \hat{\boldsymbol{F}}^*(\boldsymbol{r}, \omega) \qquad \qquad \boldsymbol{F}(\boldsymbol{r}, t) = \frac{1}{\pi} \int_0^\infty \operatorname{Re}\left[\hat{\boldsymbol{F}}(\boldsymbol{r}, \omega) e^{j\omega t}\right] d\omega$$

Reduced frequency domain representation



### Maxwell('s) Equations – Frequency Domain

$$\nabla \times \hat{\boldsymbol{H}}(\boldsymbol{r},\omega) = \hat{\boldsymbol{J}}(\boldsymbol{r},\omega) + j\omega\varepsilon\hat{\boldsymbol{E}}(\boldsymbol{r},\omega)$$

$$\nabla \times \hat{\boldsymbol{E}}(\boldsymbol{r},\omega) = -j\omega\mu\hat{\boldsymbol{H}}(\boldsymbol{r},\omega)$$

$$\nabla \cdot \hat{\boldsymbol{H}}(\boldsymbol{r}, \omega) = 0$$

$$\nabla \cdot \hat{\boldsymbol{E}}(\boldsymbol{r},\omega) = \frac{\hat{\rho}(\boldsymbol{r},\omega)}{\varepsilon}$$

We assume linearity of material relations



### **Wave Equation – Frequency Domain**


$$\Delta \hat{\boldsymbol{A}}(\boldsymbol{r},\omega) - j\omega\mu(\sigma + j\omega\varepsilon)\hat{\boldsymbol{A}}(\boldsymbol{r},\omega) = -\mu\hat{\boldsymbol{J}}_{\text{source}}(\boldsymbol{r},\omega)$$

Helmholtz('s) equation



### **Heat Balance in Time-Harmonic Steady State**

Valid for general periodic steady state



Valid for time-harmonic steady state





#### **Plane Wave**

 $\hat{m{E}}ig(m{r},\omegaig)=m{E}_0ig(\omegaig)\mathrm{e}^{-\mathrm{j}km{n}\cdotm{r}}$ Electric and magnetic fields  $\hat{\boldsymbol{H}}(\boldsymbol{r},\omega) = \frac{k}{\omega \mu} [\boldsymbol{n} \times \boldsymbol{E}_0(\omega)] e^{-jk\boldsymbol{n}\cdot\boldsymbol{r}}$ are orthogonal to propagation direction  $\boldsymbol{n} \cdot \boldsymbol{E}_0 (\omega) = 0$  $\boldsymbol{n} \cdot \boldsymbol{H}_0(\omega) = 0$  $k^2 = -\mathrm{j}\omega\mu\big(\sigma + \mathrm{j}\omega\varepsilon\big)$ Wave-number

Unitary vector representing the direction of propagation

Electric and magnetic fields are mutually orthogonal

The simplest wave solution of Maxwell('s) equations



### **Plane Wave Characteristics**

$$k = \sqrt{-j\omega\mu(\sigma + j\omega\varepsilon)}$$


$$\operatorname{Re}[k] > 0; \operatorname{Im}[k] < 0$$

$$\lambda = \frac{2\pi}{\operatorname{Re}[k]}$$

$$v_{\rm f} = \frac{\omega}{{\rm Re}[k]}$$

$$Z = \frac{\omega \mu}{k}$$

$$\delta = -\frac{1}{\mathrm{Im}[k]}$$



General isotropic material

$$k = \frac{\omega}{c_0}$$

$$\operatorname{Re}[k] > 0; \operatorname{Im}[k] = 0$$

$$\lambda = \frac{c_0}{f}$$

$$v_{\mathrm{f}} = c_{\mathrm{0}}$$

$$Z = c_0 \mu_0 = \sqrt{\frac{\mu_0}{\varepsilon_0}} \approx 377 \ \Omega$$

$$\delta \to \infty$$



### **Cycle Mean Power Density of a Plane Wave**

Power propagation coincides with phase propagation

$$\left\langle \boldsymbol{E}(\boldsymbol{r},t) \times \boldsymbol{H}(\boldsymbol{r},t) \right\rangle = \frac{1}{2} \frac{\operatorname{Re}[k]}{\omega \mu} \left| \boldsymbol{E}_{\scriptscriptstyle 0}(\omega) \right|^2 e^{2\operatorname{Im}[k]\boldsymbol{n}\cdot\boldsymbol{r}} \boldsymbol{n}$$



### Source Free Maxwell('s) Equations in Free Space

$$\nabla \times \boldsymbol{H}(\boldsymbol{r},t) = \sigma(t) * \boldsymbol{E}(\boldsymbol{r},t) + \varepsilon(t) * \frac{\partial \boldsymbol{E}(\boldsymbol{r},t)}{\partial t}$$

$$\nabla \times \boldsymbol{E}(\boldsymbol{r},t) = -\mu(t) * \frac{\partial \boldsymbol{H}(\boldsymbol{r},t)}{\partial t}$$

$$\nabla \cdot \boldsymbol{H}(\boldsymbol{r},t) = 0$$

$$\nabla \cdot \boldsymbol{E}(\boldsymbol{r},t) = 0$$

$$\begin{aligned} \left| \boldsymbol{k} \right|^2 &= k^2 = -j\omega\hat{\mu}\left(\omega\right)\left(\hat{\sigma}\left(\omega\right) + j\omega\hat{\varepsilon}\left(\omega\right)\right) \\ \hat{\boldsymbol{E}}\left(\boldsymbol{k},\omega\right) &= \frac{\boldsymbol{k}}{\omega\hat{\varepsilon}\left(\omega\right) - j\hat{\sigma}\left(\omega\right)} \times \hat{\boldsymbol{H}}\left(\boldsymbol{k},\omega\right) \\ \hat{\boldsymbol{H}}\left(\boldsymbol{k},\omega\right) &= -\frac{\boldsymbol{k}}{\omega\hat{\mu}\left(\omega\right)} \times \hat{\boldsymbol{E}}\left(\boldsymbol{k},\omega\right) \\ \boldsymbol{k} \cdot \hat{\boldsymbol{E}}\left(\boldsymbol{k},\omega\right) &= 0 \\ \boldsymbol{k} \cdot \hat{\boldsymbol{H}}\left(\boldsymbol{k},\omega\right) &= 0 \end{aligned}$$

$$\boldsymbol{F}(\boldsymbol{r},t) = \frac{1}{(2\pi)^4} \int_{\boldsymbol{k},t} \hat{\boldsymbol{F}}(\boldsymbol{k},\omega) e^{j(\boldsymbol{k}\cdot\boldsymbol{r}+\omega t)} d\boldsymbol{k} d\omega$$

Fourier's transform leads to simple algebraic equations





### **Spatial Wave Packet**

$$\left| \mathbf{k} \right|^2 = k^2 = -j\omega\hat{\mu}(\omega)(\hat{\sigma}(\omega) + j\omega\hat{\varepsilon}(\omega))$$

$$\omega = \omega(\left| \mathbf{k} \right|)$$

This can be electric or magnetic intensity

$$\mathbf{F}(\mathbf{r},t) = \frac{1}{(2\pi)^3} \int_{\mathbf{k}} \hat{\mathbf{F}}_0(\mathbf{k}) e^{j(\mathbf{k}\cdot\mathbf{r} + \omega(|\mathbf{k}|)t)} d\mathbf{k}$$
$$\mathbf{k} \cdot \hat{\mathbf{F}}_0(\mathbf{k}) = 0$$

General solution to free-space Maxwell's equations



### **Spatial Wave Packet in Vacuum**

$$\omega\left(\left|\boldsymbol{k}\right|\right) = \pm c_0 \left|\boldsymbol{k}\right|$$

$$\mathbf{k} \cdot \hat{\mathbf{F}}_{0}^{+}(\mathbf{k}) = \mathbf{k} \cdot \hat{\mathbf{F}}_{0}^{-}(\mathbf{k}) = 0$$

$$\hat{oldsymbol{F}}_{0}^{-}\left(oldsymbol{k}
ight)=\left[\hat{oldsymbol{F}}_{0}^{+}\left(-oldsymbol{k}
ight)
ight]^{*}$$
 $\hat{oldsymbol{F}}_{0}^{+}\left(oldsymbol{k}
ight)=\left[\hat{oldsymbol{F}}_{0}^{-}\left(-oldsymbol{k}
ight)
ight]^{*}$ 

$$\boldsymbol{F}(\boldsymbol{r},t) = \frac{1}{(2\pi)^3} \int_{\boldsymbol{k}} e^{j\boldsymbol{k}\cdot\boldsymbol{r}} \left[ \hat{\boldsymbol{F}}_0^+(\boldsymbol{k}) e^{jc_0t|\boldsymbol{k}|} + \hat{\boldsymbol{F}}_0^-(\boldsymbol{k}) e^{-jc_0t|\boldsymbol{k}|} \right] d\boldsymbol{k}$$

$$\hat{\boldsymbol{F}}_{0}^{+}\left(\boldsymbol{k}\right) = \frac{1}{2} \int_{\boldsymbol{r}} \left| \boldsymbol{F}\left(\boldsymbol{r},0\right) + \frac{1}{\mathrm{j} c_{0} \left|\boldsymbol{k}\right|} \frac{\partial \boldsymbol{F}\left(\boldsymbol{r},t\right)}{\partial t} \right|_{t=0} \left| \mathrm{e}^{-\mathrm{j}\boldsymbol{k}\cdot\boldsymbol{r}} \mathrm{d}\boldsymbol{r} \right|$$

$$\hat{\mathbf{F}}_{0}^{-}(\mathbf{k}) = \left[\hat{\mathbf{F}}_{0}^{+}(-\mathbf{k})\right]^{*}$$

$$\hat{\mathbf{F}}_{0}^{-}(\mathbf{k}) = \left[\hat{\mathbf{F}}_{0}^{+}(-\mathbf{k})\right]^{*}$$

$$\hat{\mathbf{F}}_{0}^{+}(\mathbf{k}) = \left[\hat{\mathbf{F}}_{0}^{-}(-\mathbf{k})\right]^{*}$$

$$\hat{\mathbf{F}}_{0}^{+}(\mathbf{k}) = \frac{1}{2} \int_{r} \left[\mathbf{F}(\mathbf{r},0) + \frac{1}{\mathrm{j}c_{0}|\mathbf{k}|} \frac{\partial \mathbf{F}(\mathbf{r},t)}{\partial t}\Big|_{t=0}\right] e^{-\mathrm{j}\mathbf{k}\cdot\mathbf{r}} d\mathbf{r}$$

$$\hat{\mathbf{F}}_{0}^{-}(\mathbf{k}) = \frac{1}{2} \int_{r} \left[\mathbf{F}(\mathbf{r},0) - \frac{1}{\mathrm{j}c_{0}|\mathbf{k}|} \frac{\partial \mathbf{F}(\mathbf{r},t)}{\partial t}\Big|_{t=0}\right] e^{-\mathrm{j}\mathbf{k}\cdot\mathbf{r}} d\mathbf{r}$$

The field is uniquely given by initial conditions



### **Spatial Wave Packet in Vacuum**

$$\omega\left(\left|\boldsymbol{k}\right|\right) = \pm c_0 \left|\boldsymbol{k}\right|$$

$$\boldsymbol{E}(\boldsymbol{r},t) = \frac{1}{(2\pi)^3} \int_{\mathbf{k}} e^{j\boldsymbol{k}\cdot\boldsymbol{r}} \left[ \hat{\boldsymbol{E}}^+(\boldsymbol{k}) e^{jc_0t|\boldsymbol{k}|} + \hat{\boldsymbol{E}}^-(\boldsymbol{k}) e^{-jc_0t|\boldsymbol{k}|} \right] d\boldsymbol{k}$$


$$\boldsymbol{H}(\boldsymbol{r},t) = -\frac{1}{(2\pi)^3} \int_{\mathbf{k}} e^{j\boldsymbol{k}\cdot\boldsymbol{r}} \frac{\boldsymbol{k}}{Z_0 |\boldsymbol{k}|} \times \left[ \hat{\boldsymbol{E}}^+ (\boldsymbol{k}) e^{jc_0 t |\boldsymbol{k}|} - \hat{\boldsymbol{E}}^- (\boldsymbol{k}) e^{-jc_0 t |\boldsymbol{k}|} \right] d\boldsymbol{k}$$

$$\mathbf{k} \cdot \hat{\mathbf{E}}^{+} \left( \mathbf{k} \right) = \mathbf{k} \cdot \hat{\mathbf{E}}^{-} \left( \mathbf{k} \right) = 0$$


Electric and magnetic field are not independent



### **Vacuum Dispersion**



Propagation in one direction



 $\boldsymbol{H}\!\left(\boldsymbol{z},\boldsymbol{t}\right) = -\frac{1}{Z_{\scriptscriptstyle 0}}\mathbf{z}_{\scriptscriptstyle 0} \times \left[\boldsymbol{E}^{\scriptscriptstyle +}\left(\boldsymbol{z}+\boldsymbol{c}_{\scriptscriptstyle 0}\boldsymbol{t}\right) - \boldsymbol{E}^{\scriptscriptstyle -}\left(\boldsymbol{z}-\boldsymbol{c}_{\scriptscriptstyle 0}\boldsymbol{t}\right)\right]$ 

1D waves in vacuum propagate without dispersion





### **Vacuum Dispersion**

In general this term does not represent translation

$$\left(\left[x,y,z\right]\pm c_{\scriptscriptstyle 0}t\right)$$

$$\boldsymbol{E}(\boldsymbol{r},t) = \frac{1}{(2\pi)^3} \int_{\mathbf{k}} e^{j\boldsymbol{k}\cdot\boldsymbol{r}} \left[ \hat{\boldsymbol{E}}^+(\boldsymbol{k}) e^{jc_0t|\boldsymbol{k}|} + \hat{\boldsymbol{E}}^-(\boldsymbol{k}) e^{-jc_0t|\boldsymbol{k}|} \right] d\boldsymbol{k}$$

Waves propagating in all directions

2D and 3D waves in vacuum always disperse = change shape in time



## **Angular Spectrum Representation**

 $\operatorname{Im}\left[k_{z}\right] < 0$ 

$$\left|\boldsymbol{k}\right|^2 = k^2 = -\mathrm{j}\omega\hat{\mu}\left(\omega\right)\left(\hat{\sigma}\left(\omega\right) + \mathrm{j}\omega\hat{\varepsilon}\left(\omega\right)\right) \qquad \qquad k_z = \pm\sqrt{k^2 - k_x^2 - k_y^2}$$

$$\begin{split} \hat{\mathbf{H}}_{0}\left(k_{x},k_{y},\omega\right) &= -\frac{\mathbf{k}}{Z\left|\mathbf{k}\right|} \times \hat{\mathbf{E}}_{0}\left(k_{x},k_{y},\omega\right) \\ \hat{\mathbf{E}}_{0}\left(k_{x},k_{y},\omega\right) &= \mathcal{F}_{x,y,t}\left\{\mathbf{E}\left(x,y,0,t\right)\right\} \\ \hat{\mathbf{E}}\left(x,y,z<0,t\right) &= \frac{1}{\left(2\pi\right)^{3}} \int_{k_{x},k_{y},\omega} e^{\mathrm{j}\left(k_{x}x+k_{y}y+\omega t\right)} \hat{\mathbf{E}}_{0}\left(k_{x},k_{y},\omega\right) e^{\mathrm{j}\sqrt{k^{2}-k_{x}^{2}-k_{y}^{2}}z} \mathrm{d}k_{x} \mathrm{d}k_{y} \mathrm{d}\omega \\ \hat{\mathbf{E}}\left(x,y,z>0,t\right) &= \frac{1}{\left(2\pi\right)^{3}} \int_{k_{x},k_{y},\omega} e^{\mathrm{j}\left(k_{x}x+k_{y}y+\omega t\right)} \hat{\mathbf{E}}_{0}\left(k_{x},k_{y},\omega\right) e^{-\mathrm{j}\sqrt{k^{2}-k_{x}^{2}-k_{y}^{2}}z} \mathrm{d}k_{x} \mathrm{d}k_{y} \mathrm{d}\omega \\ \hat{\mathbf{k}} \cdot \hat{\mathbf{E}}_{0} &= 0 \end{split}$$

General solution to free-space Maxwell's equations



### **Propagating vs Evanescent Waves**

$$k_x^2 + k_y^2 < k^2$$

These waves propagate and can carry information to far distances

$$k_x^2 + k_y^2 > k^2$$

These waves exponentially decay in amplitude and cannot carry information to far distances

Field picture losses it resolution with distance from the source plane



#### **Paraxial Waves**

$$\hat{\boldsymbol{E}}_{0}\left(k_{x},k_{y},\omega\right) \qquad \\ \hat{\boldsymbol{k}}_{x}^{2}+k_{y}^{2}\ll k^{2} \qquad \\ \sqrt{k^{2}-k_{x}^{2}-k_{y}^{2}}\approx k-\frac{1}{2k}\left(k_{x}^{2}+k_{y}^{2}\right)$$

$$\begin{split} \boldsymbol{E} \left( x,y,z > 0,t \right) &= \frac{1}{\left( 2\pi \right)^3} \int\limits_{k_x,k_y,\omega} \mathrm{e}^{\mathrm{j} \left( k_x x + k_y y - kz + \omega t \right)} \hat{\boldsymbol{E}}_0 \left( k_x,k_y,\omega \right) \mathrm{e}^{\mathrm{j} \frac{1}{2k} \left( k_x^2 + k_y^2 \right) z} \mathrm{d}k_x \mathrm{d}k_y \mathrm{d}\omega \\ \boldsymbol{k} \cdot \hat{\boldsymbol{E}}_0 &= 0 \end{split}$$
 Propagates almost as a planewave

$$\mathbf{z}_{0}\cdot\hat{\boldsymbol{E}}_{0}\approx0$$






#### **Gaussian Beam**

$$\hat{\boldsymbol{E}}_{0\perp}\left(k_{x},k_{y},\omega\right)=\mathbf{A}_{0\perp}\pi w_{0}^{2}e^{-\frac{1}{4}w_{0}^{2}\left(k_{x}^{2}+k_{y}^{2}\right)}$$





Approximates radiation of sources large in comparison to wavelength



Planewave-like


propagation




Gaussian profile

in amplitude

### **Gaussian Beam**



$$w(z) = w_0 \sqrt{1 + \left(\frac{z}{z_R}\right)^2}$$



Rayleigh's distance

$$z_{R} = \frac{1}{2}kw_{0}^{2} = \frac{\pi w_{0}^{2}}{\lambda}$$



 $\pi w_{_0}$ 



#### **Gaussian Beam – Time-Harmonic Case**

$$\left\langle \boldsymbol{S} \right\rangle = \frac{1}{2} \operatorname{Re} \left[ \hat{\boldsymbol{E}} \left( x, y, z, \omega \right) \times \hat{\boldsymbol{H}}^* \left( x, y, z, \omega \right) \right] = \mathbf{z}_0 S_0 \frac{w_0^2}{w^2 \left( z \right)} e^{-\frac{2\rho^2}{w^2 \left( z \right)}}$$

86.5 % of power flows through the beam width

$$w\!\left(z\right)\!=w_{\scriptscriptstyle 0}\sqrt{1+\!\left(\frac{z}{z_{\scriptscriptstyle R}}\!\right)^{\!\!2}}$$

Power density at origin






### **Material Dispersion**



 $\varepsilon(\tau) = 0, \tau < 0$ 

#### Stability requirement

$$\varepsilon(\tau) \to 0, \tau \to \infty$$



$$\boldsymbol{B}(\boldsymbol{r},t) = \int_{-\infty}^{\infty} \mu(\tau) \boldsymbol{H}(\boldsymbol{r},t-\tau) d\tau$$

$$\boldsymbol{J}(\boldsymbol{r},t) = \int_{-\infty}^{\infty} \sigma(\tau) \boldsymbol{E}(\boldsymbol{r},t-\tau) d\tau$$

$$\hat{\boldsymbol{D}}(\boldsymbol{r},\omega) = \hat{\varepsilon}(\omega)\hat{\boldsymbol{E}}(\boldsymbol{r},\omega)$$


$$\hat{\boldsymbol{B}}(\boldsymbol{r},\omega) = \hat{\mu}(\omega)\hat{\boldsymbol{H}}(\boldsymbol{r},\omega)$$

$$\hat{\boldsymbol{J}}(\boldsymbol{r},\omega) = \hat{\sigma}(\omega)\hat{\boldsymbol{E}}(\boldsymbol{r},\omega)$$

Even single planewave undergoes time dispersion when materials are present



### **Lorentz's Dispersion Model**



Dispersion model able to describe vast amount of natural materials





### **Drude's Dispersion Model**

Special case of Lorentz's dispersion



$$\omega_0 = 0$$

$$\omega_{\rm p}^2 = \frac{\sigma_0 \Gamma}{\varepsilon_0}$$

#### Permittivity model

$$\varepsilon(\omega) = \varepsilon_0 \left( 1 - \frac{\omega_p^2}{\omega(\omega - j\Gamma)} \right)$$



#### Conductivity model

$$\sigma(\omega) = \frac{\sigma_0}{1 + j\frac{\omega}{\Gamma}}$$


#### Collisionless plasma


$$\frac{\Gamma}{\omega} \ll 1 \Longrightarrow \varepsilon(\omega) \approx \varepsilon_0 \left( 1 - \frac{\omega_p^2}{\omega^2} \right)$$

Dispersion model describing neutral plasma



### **Appleton's Dispersion Model**






Dispersion model describing magnetized neutral plasma





### **Propagation in Appleton's Dispersion Model**




Fundamental modes are circularly polarized waves  $\frac{k_z^2}{k_0^2} = 1 - \frac{\omega_{\rm p}^2}{\omega \left(\omega \pm \omega_{\rm c}\right)}$   $\hat{E}_x = \mp {\rm j} \hat{E}_y$ 

Dispersion model describing magnetized neutral plasma



### **Radiation**





### **Time-Harmonic Electric Dipole**

$$\hat{\boldsymbol{P}}(\boldsymbol{r},\omega) = \mathbf{z}_0 p_z(\omega) \delta(x) \delta(y) \delta(z)$$

$$\rho(\boldsymbol{r},\omega) \approx 0$$

$$\hat{\boldsymbol{A}}(\boldsymbol{r},\omega) = \mathrm{j} Z_0 k^2 \left(\boldsymbol{r}_0 \cos \theta - \theta_0 \sin \theta\right) p_z \left(\omega\right) \frac{\mathrm{e}^{-\mathrm{j}kr}}{4\pi kr}$$

$$\hat{\boldsymbol{H}}\left(\boldsymbol{r},\omega\right) = c_0 k^3 \varphi_0 \sin\theta \left(-1 + \frac{\mathrm{j}}{kr}\right) p_z\left(\omega\right) \frac{\mathrm{e}^{-\mathrm{j}kr}}{4\pi kr}$$


$$\hat{\boldsymbol{E}}\left(\boldsymbol{r},\omega\right) = Z_{0}c_{0}k^{3}\left[2\boldsymbol{r}_{0}\cos\theta\left(\frac{\mathrm{j}}{kr} + \frac{1}{k^{2}r^{2}}\right) + \theta_{0}\left(-1 + \frac{\mathrm{j}}{kr} + \frac{1}{k^{2}r^{2}}\right)\sin\theta\right]p_{z}\left(\omega\right)\frac{\mathrm{e}^{-\mathrm{j}kr}}{4\pi kr}$$

Elementary source of radiation





### **Time-Harmonic Electric Dipole - Field Zones**



Static, quasi-static and fully dynamic terms all appear in the formula



### **Time-Harmonic Electric Dipole - Radiation Zone**

$$\hat{\boldsymbol{P}}\!\left(\boldsymbol{r},\omega\right) = \mathbf{z}_{\scriptscriptstyle 0} p_{\scriptscriptstyle z}\!\left(\omega\right) \delta\!\left(x\right) \delta\!\left(y\right) \delta\!\left(z\right)$$



 $\hat{m{E}}_{\infty}\left(m{r},\omega
ight)pprox -Z_{0}c_{0}k^{3} heta_{0}p_{z}\left(\omega
ight)rac{\mathrm{e}^{-\mathrm{j}kr}}{4\pi kr}\sin heta_{z}$ 

$$m{r}_{0}\cdot\hat{m{E}}_{\infty}pprox0$$

$$\hat{m{H}}_{\infty}\left(m{r},\omega
ight)pproxrac{1}{Z_{0}}m{r}_{\!_{0}} imes\hat{m{E}}_{\!_{\infty}}\left(m{r},\omega
ight)$$

$$\left\langle oldsymbol{S}_{\infty} 
ight
angle = rac{1}{2} \operatorname{Re} \left[ \hat{oldsymbol{E}}_{\infty} imes \hat{oldsymbol{H}}_{\infty}^{*} 
ight] = rac{1}{2Z_{0}} \left| \hat{oldsymbol{E}}_{\infty} \left( oldsymbol{r}, \omega 
ight) 
ight|^{2} oldsymbol{r}_{0}^{*}$$

#### Radiated power [W]

$$P_{\mathrm{rad}} = \frac{c_{\scriptscriptstyle 0}^2 Z_{\scriptscriptstyle 0} k^4}{12\pi} \Big| p_{\scriptscriptstyle z} \left(\omega\right) \Big|^2$$

Farfield has a planewave-like geometry



### **Time-Harmonic Electric Dipole – General Case**

$$\hat{\boldsymbol{P}}(\boldsymbol{r},\omega) = \hat{\boldsymbol{p}}(\omega)\delta(\boldsymbol{r}-\boldsymbol{r}')$$



$$R=r-r'$$

$$\hat{\boldsymbol{H}}(\boldsymbol{r},\omega) = c_0 k^3 \left(\frac{\boldsymbol{R}}{R} \times \hat{\boldsymbol{p}}\right) \left(1 + \frac{1}{jkR}\right) \frac{e^{-jkR}}{4\pi kR}$$

$$\hat{\boldsymbol{E}}(\boldsymbol{r},\omega) = Z_0 c_0 k^3 \left[ -\frac{\boldsymbol{R}}{R} \times \left( \frac{\boldsymbol{R}}{R} \times \hat{\boldsymbol{p}} \right) + \left( 3 \frac{\boldsymbol{R}}{R} \left[ \hat{\boldsymbol{p}} \cdot \frac{\boldsymbol{R}}{R} \right] - \hat{\boldsymbol{p}} \right) \left( \frac{1}{k^2 R^2} + \frac{\mathrm{j}}{kR} \right) \right] \frac{\mathrm{e}^{-\mathrm{j}kR}}{4\pi kR}$$


$$R = |\boldsymbol{r} - \boldsymbol{r}'|$$

Elementary source of radiation





### **General Radiator**





### Field in Radiation Zone - General Case FD


$$kR \gg 1 \quad \land \quad r \gg r'$$



$$\hat{m{A}}_{\infty}\left(m{r},\omega
ight)pproxrac{\mu_{0}}{4\pi}rac{\mathrm{e}^{-\mathrm{j}kr}}{r}\int_{V'}\hat{m{J}}\left(m{r}',\omega
ight)\mathrm{e}^{\mathrm{j}k_{0}\mathbf{r}_{0}\cdotm{r}'}\mathrm{d}\,V'$$

$$\hat{m{H}}_{\infty}\left(m{r},\omega
ight)pprox-rac{\mathrm{j}\omega}{Z_{0}}\mathbf{r}_{\!_{0}} imes\hat{m{A}}_{\!_{\infty}}\left(m{r},\omega
ight)$$

$$\left\langle \boldsymbol{S}_{_{\infty}}\right\rangle =\frac{1}{2Z_{_{0}}}\,\omega^{2}\left|\boldsymbol{\mathbf{r}}_{_{0}}\times\hat{\boldsymbol{A}}_{_{\infty}}\left(\boldsymbol{r},\omega\right)\right|^{2}\,\boldsymbol{\mathbf{r}}_{_{0}}$$



Farfield has a planewave-like geometry



### Field in Radiation Zone – General Case TD


$$egin{aligned} oldsymbol{A}_{\infty}\left(oldsymbol{r},t
ight) &pprox rac{\mu}{4\pi r} \int_{V'} oldsymbol{J} \left(oldsymbol{r}',t-rac{r}{c_0}+rac{\mathbf{r}_0\cdotoldsymbol{r}'}{c_0}
ight) \mathrm{d}\,V' \ oldsymbol{E}_{\infty} &pprox -Z_0\left(\mathbf{r}_0 imesoldsymbol{H}_{\infty}\left(oldsymbol{r},t
ight) pprox -rac{1}{Z_0}\mathbf{r}_0 imes\dot{\mathbf{A}}_{\infty}\left(oldsymbol{r},t
ight) \ oldsymbol{E}_{\infty}\left(oldsymbol{r},t
ight) &pprox \mathbf{r}_0 imes\left(\mathbf{r}_0 imes\dot{\mathbf{A}}_{\infty}\left(oldsymbol{r},t
ight)
ight) \ oldsymbol{S}_{\infty} &pprox rac{1}{Z_0} \left|\mathbf{r}_0 imes\dot{\mathbf{A}}_{\infty}\left(oldsymbol{r},t
ight)
ight|^2\mathbf{r}_0 \end{aligned}$$

Farfield has a planewave-like geometry



# **Radiation Zone = Rays**


$$\hat{\boldsymbol{A}}_{\infty}\left(\boldsymbol{r},\omega\right) pprox rac{\mu_{0}}{4\pi} rac{\mathrm{e}^{-\mathrm{j}kr}}{r} \int_{V'} \hat{\boldsymbol{J}}\left(\boldsymbol{r}',\omega\right) \mathrm{e}^{\mathrm{j}k_{0}\mathbf{r}_{0}\cdot\boldsymbol{r}'} \mathrm{d}\,V'$$



Radiation diagram is formed by Fourier(`s) transform of sources



## **Angular Spectrum Representation (Sources)**



General solution to free-space Maxwell's equations



## **Angular Spectrum in Radiation Zone**

$$\mathbf{F}\left(x,y,z>0,\omega\right) = \mathcal{F}_{k_{x},k_{y}}^{-1}\left\{\hat{\mathbf{G}}\left(k_{x},k_{y}\right)e^{-\mathrm{j}k_{z}z}\right\}$$

$$kr \to \infty \quad \downarrow \quad k_z = \sqrt{k^2 - k_x^2 - k_y^2}$$

$$\operatorname{Im}[k_z] < 0$$

$$m{r}_0 = rac{igl[x,y,zigr]}{r}$$

$$oldsymbol{F}_{\infty}\left(oldsymbol{r},\omega
ight)=rac{1}{\left(2\pi
ight)^{2}}\int\limits_{k^{2}>k_{x}^{2}+k_{y}^{2}}\hat{oldsymbol{G}}\left(k_{x},k_{y}
ight)\mathrm{e}^{\mathrm{j}kr\left[rac{k_{x}}{k}r_{0x}+rac{k_{y}}{k}r_{0y}-rac{k_{z}}{k}r_{0z}
ight]}\mathrm{d}k_{x}\mathrm{d}k_{y}$$

$$kr \to \infty$$

 $kr 
ightarrow \infty$  Stationary phase method

$$\boldsymbol{F}_{\infty}\left(\boldsymbol{r},\omega\right) = \frac{\mathrm{j}\,kr_{0z}}{2\pi}\,\hat{\boldsymbol{G}}\left(-kr_{0x},-kr_{0y}\right)\frac{\mathrm{e}^{-\mathrm{j}kr}}{r}$$

Farfield is made of propagating planewaves



## **Angular Spectrum in Radiation Zone**

#### 4D Fourier('s) transform

$$\hat{\boldsymbol{J}}\!\left(k_{\boldsymbol{x}},k_{\boldsymbol{y}},k_{\boldsymbol{z}},\omega\right) = \mathcal{F}_{\boldsymbol{x},\boldsymbol{y},\boldsymbol{z},t}\left\{\boldsymbol{J}\!\left(\boldsymbol{x},\boldsymbol{y},\boldsymbol{z},t\right)\!\right\}$$

$$m{H}_{\infty}\left(m{r},t
ight)pprox\mathcal{F}_{\omega}^{-1}\left\{\!-rac{\mathrm{j}\,k}{4\pi}m{r}_{\!\scriptscriptstyle{0}}\! imes\!\hat{m{J}}\!\left(\!-k_{\!\scriptscriptstyle{0}}m{r}_{\!\scriptscriptstyle{0}},\omega
ight)\!rac{\mathrm{e}^{-\mathrm{j}k_{\!\scriptscriptstyle{0}}r}}{r}\!
ight\}$$

$$m{E}_{\infty}\left(m{r},t
ight)pprox\mathcal{F}_{\omega}^{-1}\left\{rac{\mathrm{j}kZ_{0}}{4\pi}m{r}_{\!0} imesm{r}_{\!0} imes\hat{m{J}}\left(-k_{\!0}m{r}_{\!0},\omega
ight)rac{\mathrm{e}^{-\mathrm{j}k_{\!0}r}}{r}
ight\}$$

$$\mathbf{r}_0 = \frac{\left[x, y, z\right]}{r}$$

Farfield is made of propagating planewaves



## **Planar Material Boundary**

$$k_z = \sqrt{k^2 - k_x^2 - k_y^2}$$

Incident wave

Reflected  $(1 \rightarrow 1)$  / Transmitted  $(2 \rightarrow 1)$  wave

$$\begin{split} \boldsymbol{H} \left( z < 0 \right) &= \mathcal{F}_{k_{x},k_{y}}^{-1} \left\{ \boldsymbol{H}_{1}^{+} \left( k_{x}, k_{y}, \omega \right) \mathrm{e}^{-\mathrm{j}k_{z1}z} + \boldsymbol{H}_{1}^{-} \left( k_{x}, k_{y}, \omega \right) \mathrm{e}^{\mathrm{j}k_{z1}z} \right\} \\ \boldsymbol{E} \left( z < 0 \right) &= \mathcal{F}_{k_{x},k_{y}}^{-1} \left\{ Z_{1} \frac{\left[ k_{x}, k_{y}, -k_{z1} \right] \times \boldsymbol{H}_{1}^{+} \left( k_{x}, k_{y}, \omega \right)}{k_{1}} \mathrm{e}^{-\mathrm{j}k_{z1}z} + Z_{1} \frac{\left[ k_{x}, k_{y}, k_{z1} \right] \times \boldsymbol{H}_{1}^{-} \left( k_{x}, k_{y}, \omega \right)}{k_{1}} \mathrm{e}^{\mathrm{j}k_{z1}z} \right\} \end{split}$$

$$\begin{split} \boldsymbol{H} \Big( z > 0 \Big) &= \mathcal{F}_{k_{x},k_{y}}^{-1} \left\{ \boldsymbol{H}_{2}^{+} \Big( k_{x}, k_{y}, \omega \Big) \mathrm{e}^{-\mathrm{j}k_{z}z^{z}} + \boldsymbol{H}_{2}^{-} \Big( k_{x}, k_{y}, \omega \Big) \mathrm{e}^{\mathrm{j}k_{z}z^{z}} \right\} \\ \boldsymbol{E} \Big( z > 0 \Big) &= \mathcal{F}_{k_{x},k_{y}}^{-1} \left\{ Z_{2} \frac{\left[ k_{x}, k_{y}, -k_{z2} \right] \times \boldsymbol{H}_{2}^{+} \left( k_{x}, k_{y}, \omega \right)}{k_{2}} \mathrm{e}^{-\mathrm{j}k_{z}z^{z}} + Z_{2} \frac{\left[ k_{x}, k_{y}, k_{z2} \right] \times \boldsymbol{H}_{2}^{-} \left( k_{x}, k_{y}, \omega \right)}{k_{2}} \mathrm{e}^{\mathrm{j}k_{z}z^{z}} \right\} \end{split}$$

Boundary is at z = 0

Reflected  $(2 \rightarrow 2)$  / Transmitted  $(1 \rightarrow 2)$  wave

Incident wave

Field is composed of incident, reflected and transmitted waves

## **Planar Material Boundary – Boundary Conditions**

$$\begin{split} \left[k_{x},k_{y},\mp k_{z1}\right]\cdot\mathbf{H}_{1}^{\pm} &= 0 & \left[k_{x},k_{y},\mp k_{z2}\right]\cdot\mathbf{H}_{2}^{\pm} &= 0 \\ \mathbf{z}_{0}\times\boldsymbol{H}_{1}^{+} + \mathbf{z}_{0}\times\boldsymbol{H}_{1}^{-} &= \mathbf{z}_{0}\times\boldsymbol{H}_{2}^{+} + \mathbf{z}_{0}\times\boldsymbol{H}_{2}^{-} \\ Z_{1}\frac{\mathbf{z}_{0}\times\left[k_{x},k_{y},-k_{z1}\right]\times\boldsymbol{H}_{1}^{+}}{k_{1}} + Z_{1}\frac{\mathbf{z}_{0}\times\left[k_{x},k_{y},k_{z1}\right]\times\boldsymbol{H}_{1}^{-}}{k_{1}} &= \\ Z_{2}\frac{\mathbf{z}_{0}\times\left[k_{x},k_{y},-k_{z2}\right]\times\boldsymbol{H}_{2}^{+}}{k_{2}} + Z_{2}\frac{\mathbf{z}_{0}\times\left[k_{x},k_{y},k_{z2}\right]\times\boldsymbol{H}_{2}^{-}}{k_{2}} \end{split}$$

 $k_x, k_y$  are equal on both sides


$$k_z = \sqrt{k^2 - k_x^2 - k_y^2}$$

$$\operatorname{Im}[k_z] < 0$$

Relations valid for both propagative and evanescent waves



## **Perpendicular Incidence – Matrix Form**




Electromagnetic Field Theory 2



## **Perpendicular Incidence – Interesting Cases**

Wavelength inside the slab

Transparent dielectric layer




Bragg's mirror (dielectric mirror)

$$k_{_{0}}\left(n_{_{\!\!1}}d_{_{\!\!1}}+n_{_{\!\!2}}d_{_{\!\!2}}\right)=N\pi$$
 Alternating dielectric layers

Technically important special cases



# **Oblique Incidence – TM / TE Case**







# **Oblique Incidence – TM Case**

$$k_y = 0$$

$$H_x = 0$$

$$H_z = 0$$

$$\begin{split} R_{1 \to 1}^{\mathrm{TM}} &= \frac{E_{1x}^{-}}{E_{1x}^{+}} = \frac{\sqrt{1 - \frac{k_{x}^{2}}{k_{2}^{2}}} Z_{2} - \sqrt{1 - \frac{k_{x}^{2}}{k_{1}^{2}}} Z_{1}}{\sqrt{1 - \frac{k_{x}^{2}}{k_{2}^{2}}} Z_{2} + \sqrt{1 - \frac{k_{x}^{2}}{k_{1}^{2}}} Z_{1}} \\ T_{1 \to 2}^{\mathrm{TM}} &= \frac{E_{2x}^{+}}{E_{1x}^{+}} = \frac{2Z_{2}\sqrt{1 - \frac{k_{x}^{2}}{k_{2}^{2}}}}{\sqrt{1 - \frac{k_{x}^{2}}{k_{2}^{2}}} Z_{2} + \sqrt{1 - \frac{k_{x}^{2}}{k_{1}^{2}}} Z_{1}} \end{split}$$

Generalization of reflection and transmission to oblique incidence




# **Oblique Incidence – TM Case**

$$k_y = 0$$

$$H_x = 0$$

$$H_z = 0$$

#### Brewster's angle



Simplification for pure dielectrics

$$\frac{k_{x}}{k_{1}} = \left(1 + \frac{\varepsilon_{1}}{\varepsilon_{2}}\right)^{-\frac{1}{2}}$$

Can be used for polarizing unpolarizaed light beams



# **Oblique Incidence – TE Case**

$$k_y = 0$$

$$E_x = 0$$

$$E_z = 0$$

$$\begin{split} R_{1 \to 1}^{\mathrm{TE}} &= \frac{E_{1y}^{-}}{E_{1y}^{+}} = \frac{\sqrt{1 - \frac{k_{x}^{2}}{k_{1}^{2}}} Z_{2} - \sqrt{1 - \frac{k_{x}^{2}}{k_{2}^{2}}} Z_{1}}{\sqrt{1 - \frac{k_{x}^{2}}{k_{1}^{2}}} Z_{2} + \sqrt{1 - \frac{k_{x}^{2}}{k_{2}^{2}}} Z_{1}} \\ T_{1 \to 2}^{\mathrm{TE}} &= \frac{E_{2y}^{+}}{E_{1y}^{+}} = \frac{2Z_{2}\sqrt{1 - \frac{k_{x}^{2}}{k_{1}^{2}}}}{\sqrt{1 - \frac{k_{x}^{2}}{k_{1}^{2}}} Z_{2} + \sqrt{1 - \frac{k_{x}^{2}}{k_{2}^{2}}} Z_{1}} \end{split}$$

Generalization of reflection and transmission to oblique incidence




# **Oblique Incidence – TE Case**

$$k_{y} = 0$$

$$E_{x} = 0$$

$$E_z = 0$$

#### Brewster's angle



#### Simplification for pure magnetics

$$\frac{k_x}{k_1} = \left(1 + \frac{\mu_1}{\mu_2}\right)^{-\frac{1}{2}}$$

Unrealistic scenario for natural materials





# **Oblique Incidence – Total Reflection**

$$\frac{k_x}{k_1} > \frac{k_2}{k_1} = \frac{n_2}{n_1} < 1$$



$$\left| R_{\scriptscriptstyle 1 \rightarrow 1}^{\scriptscriptstyle \mathrm{TM}} \right| = \left| R_{\scriptscriptstyle 1 \rightarrow 1}^{\scriptscriptstyle \mathrm{TE}} \right| = 1$$


Valid for both, the TM and the TE case



#### **Guided TEM Wave**


Wave propagation identical to a planewave

$$k^2 = -j\omega\mu(\sigma + j\omega\varepsilon)$$



$$\hat{m{H}}ig(m{r},\omegaig) = m{H}_{\perp}ig(x,y,\omegaig)\mathrm{e}^{-\mathrm{j}kz}$$

Geometry of a planewave



$$\Delta_{\perp} \boldsymbol{E}_{\perp} = 0$$
$$\Delta_{\perp} \boldsymbol{H}_{\perp} = 0$$

 $\mathbf{n} \times \mathbf{E}_{\perp} = 0$ 

Boundary condition on the conductor



Generalization of a planewave



### **Circuit Parameters of the TEM Wave**

**Enclosing conductor** 

$$\hat{U}(z,\omega) = \hat{U}_{0}(\omega)e^{-jkz}$$

$$\hat{I}(z,\omega) = \hat{I}_{0}(\omega) e^{-jkz}$$

$$\hat{I}_{0}(\omega) = \oint_{l} \boldsymbol{H}_{\perp} \cdot \mathrm{d}\boldsymbol{l} = \frac{k}{\omega\mu} \cdot \frac{Q_{\mathrm{pul}}}{\varepsilon}$$

$$\hat{U}_{0}(\omega) = -\int_{A}^{B} \mathbf{E}_{\perp} \cdot d\mathbf{l} = \frac{\omega \mu}{k} \cdot \frac{\Phi_{\text{pul}}}{\mu}$$

$$Z_{\text{TRL}} = \frac{\hat{U_{0}}\left(\omega\right)}{\hat{I_{0}}\left(\omega\right)} = \frac{\omega\mu}{k} \cdot \frac{\varepsilon}{C_{\text{pul}}} = \frac{\omega\mu}{k} \cdot \frac{L_{\text{pul}}}{\mu} = \sqrt{\frac{L_{\text{pul}}}{C_{\text{pul}}}}$$

$$v_{\rm phase} = \frac{1}{\sqrt{C_{\rm pul}L_{\rm pul}}} = \frac{1}{\sqrt{\varepsilon\mu}}$$

Between conductors

Per unit length

Velocity of phase propagation





# **The Telegraph Equations**

$$\frac{\partial U(z,t)}{\partial z} = -L_{\text{pul}} \frac{\partial I(z,t)}{\partial t}$$

$$\frac{\partial I\left(z,t\right)}{\partial z} = -C_{\text{pul}} \frac{\partial U\left(z,t\right)}{\partial t}$$

Circuit analog of Maxwell's equations




#### **Guided TE and TM Waves**

Wave propagation differs from a planewave

$$\hat{\boldsymbol{E}}\left(\boldsymbol{r},\omega\right) = \left[\boldsymbol{E}_{\perp}\left(\boldsymbol{r}_{\!_{\perp}},\omega\right) + \boldsymbol{z}_{\!_{0}}E_{z}\left(\boldsymbol{r}_{\!_{\perp}},\omega\right)\right]\mathrm{e}^{-\mathrm{j}k_{z}z}$$

$$\hat{m{H}}\left(m{r},\omega
ight) = \left[m{H}_{\perp}\left(m{r}_{\!_{\perp}},\omega
ight) + m{z}_{\!_{0}}H_{z}\left(m{r}_{\!_{\perp}},\omega
ight)
ight]\mathrm{e}^{-\mathrm{j}k_{z}z}$$







$$\boldsymbol{H}_{\!\scriptscriptstyle \perp} = -\frac{1}{k_{\scriptscriptstyle \perp}^2} \! \! \left( \mathrm{j} k_{\!\scriptscriptstyle z} \nabla_{\!\scriptscriptstyle \perp} H_{\!\scriptscriptstyle z} + \! \left( \sigma \! + \! \mathrm{j} \omega \varepsilon \right) \! \boldsymbol{z}_{\!\scriptscriptstyle 0} \times \nabla_{\!\scriptscriptstyle \perp} E_{\!\scriptscriptstyle z} \right) \!$$



$$\Delta_{\perp} E_z + k_{\perp}^2 E_z = 0$$

$$\Delta_{\perp}H_{z}+k_{\perp}^{2}H_{z}=0$$






# PEC Waveguides – pure TE, TM modes

Impedances differ from those of a planewave

Boundary condition on the conductor

$$\boldsymbol{n} \times \hat{\boldsymbol{E}} = 0$$





- Wavenumbers  $k_{\perp} > 0$  form discrete set
- Modes are orthogonal in waveguide cross-section
- Modes form a complete set in waveguide cross-section

TEM mode must be completed with TE and TM modes to form a complete set



#### Lukas Jelinek

Ver. 2017/04/03

